



1. In **Mode Control**, Select **Raw Mode**;




2. In **PPG Settings** --> **System Control**: select PPG2 Power Down.

3. In **PPG Settings** --> **Frame Rate Settings**: Choose the frame rate you want. Normally, select Clock as 32768HZ, Desired Frame Rate 250fps. Remember to change the **config.json** file if you choose to run the binary file parser program.

```
{
  "clock": 32768,
  "desired_frame_rate": 250,
  "auto_detect": true,
  "file_path": "",
  "search_pattern": "*.bin",
  "output_directory": "./",
  "logging": "info",
  "logging_directory": "./logging"
}
```



4. In **ECG Channel**, unselect ECG Enable.



5. Click the **Logging menu** on the top of the window, choose 'file', and select the directory you want to keep the logging files in. If you use the binary parser, you have to put the binary parser in the same directory as the logging .bin file.

